Updating a Future Impact I to v3.00

There are two parts to this process:

- 1. Backing up your old programs from your pedal to your computer (optional);
- 2. Installing the v3.00 firmware on your pedal.

Please consult the **Installing the Editor** section in the v3.00 User Guide if you do not yet know how to connect your FI to your computer or if you need more detailed instructions on how to install the Editor and how to update the FI firmware.

Backing up your old programs

If you do not already have your programs stored on your computer but wish to preserve them then you must carry out the steps listed below. Backing up your files requires v2.20 of the Editor and either v2.20 or v2.22 of the FI firmware; if you already have these installed then, after carrying out step 1 in this section, you can skip straight to step 6. If you don't want to or don't need to back up your programs then you can skip straight to **Installing the v3.00 firmware**.

- Make a note of any changes to the 99 programs' parameters made using the PARAMETER and EDIT dials. (You can use the tables on pages 3-8 to do this.) Unfortunately these changes are not stored as part of the file but are stored locally on the pedal and will be erased during the update process. The program files are only backed up at their default settings (5);
- Go to http://pandamidi.com/support and download v2.20 of the Editor and v2.22 of the FI firmware;
- 3. Install the **v2.20** version of the Editor;
- 4. Power on the FI holding both footswitches to put it into update mode;
- 5. In the **File** menu of the Editor, select **Firmware Update** and select the file **fi222.ldr** when prompted. When done, power the FI off and on.
- 6. In the **File** menu of the Editor, select **Save All Programs from FI to Files** to back up the programs from your pedal to your computer.

Installing the v3.00 firmware

Important: please read all of the following steps carefully before doing anything, paying particular attention to step 5.

Note: You can install the firmware update using your currently-installed version of the Editor. However, afterwards you will need to install the v3.00 Editor in order to be able to *use* the FI.

- Go to http://pandamidi.com/support and download the v3.00 Distribution Package which contains the v3.00 Editor, the v3.00 firmware and the v3.00 factory default soundset.
- 2. Launch your currently-installed version of the Editor;
- 3. Power on the FI holding both footswitches to put it into update mode;
- 4. In the **File** menu of the Editor, select **Firmware Update** and select the file **fi300.ldr** when prompted to update the FI firmware to v3.00;
- 5. Reboot the FI to the boot menu by holding down PROGRAM while powering on. **This step is absolutely essential!** Starting up the FI with the v3.00 firmware whilst the the pedal still contains v2.2x files will cause crashing. Booting the pedal in the boot menu mode prevents the startup program from loading but still allows you to write files to the pedal.
- 6. In the **File** menu of the Editor, select **Write All Programs from Files to FI** and choose the folder containing the new v3.00 factory soundset when prompted.

If you wish to write any of your backed-up programs back onto the FI, you can do so by going to the **File** menu and selecting **Write Program from File to FI**. (See the relevant sections on **The File Menu** in the v3.00 User Guide for full details on how to do this.)

Program	Attack	Decay	Env. Depth	Dynamics	Cutoff	Resonance	Balance	Level	Effect
01									
02									
03									
04									
05									
06									
07									
08									
09									
10									
11									
12									
13									
14									
15									
16									
17									
18									
19									

20					
21					
22					
23					
24					
25					
26					
27					
28					
29					
30					
31					
32					
33					
34					
35					
36					
37					
38					
39					

40					
41					
42					
43					
44					
45					
46					
47					
48					
49					
40					
41					
42					
43					
44					
45					
46					
47					
48					
49					

50					
51					
52					
53					
54					
55					
56					
57					
58					
59					
50					
51					
52					
53					
54					
55					
56					
57					
58					
59					

60					
61					
62					
63					
64					
65					
66					
67					
68					
69					
70					
71					
72					
73					
74					
75					
76					
77					
78					
79					

80					
81					
82					
83					
84					
85					
86					
87					
88					
89					
90					
91					
92					
93					
94					
95					
96					
97					
98					
99					